



Lecture 11: Persistent Memory Databases

CREATING THE NEXT®

Administrivia

Assignment 2 and Sheet 2: Due on October 8th @ 11:59pm Start preparing for mid-term exam

- Assignat



Today's Agenda

Persistent Memory Databases

- 1.1 Recap
- 1.2 Disk-oriented vs In-Memory DBMSs
- 1.3 Persistent Memory DBMSs
- 1.4 Storage Engine Architectures



Recap

Larger-than-Memory Databases

- Allow an in-memory DBMS to store/access data on disk <u>without</u> bringing back all the slow parts of a disk-oriented DBMS.
 - Minimize the changes that we make to the DBMS that are required to deal with disk-resident data.
 - It is better to have only the **buffer manager** deal with moving data around
 - Rest of the DBMS can assume that data is in DRAM.
- Need to be aware of hardware access methods
 - ► In-memory Access = **Tuple**-Oriented.
 - ► Disk Access = **Block**-Oriented.



Design Decisions

Run-time Operation

Cold Data Identification: When the DBMS runs out of DRAM space, what data should we evict?

Eviction Policies

- Timing: When to evict data?
- Evicted Tuple Metadata: During eviction, what meta-data should we keep in DRAM to track disk-resident data and avoid false negatives?

Data Retrieval Policies

- Granularity: When we need data, how much should we bring in?
- Merging: Where to put the retrieved data?

Reference





Disk-oriented vs In-Memory DBMSs

20105

Background

- Much of the development history of DBMSs is about dealing with the limitations of hardware.
- Hardware was much different when the original DBMSs were designed in 1970s:
 - Uniprocessor (single-core CPU)
 - DRAM capacity was very limited.
 - The database had to be stored on disk.
 - Disks were even slower than they are now.



Background

- But now DRAM capacities are large enough that most databases can fit in memory.
 - Structured data sets are smaller.
- We need to understand why we can't always use a "traditional" disk-oriented DBMS with a large cache to get the best performance.

2 serm

Stadeorullan



Disk-Oriented DBMS


- The primary storage location of the database is on non-volatile storage (e.g., HDD, SSD).
- The database is organized as a set of fixed-length **pages** (aka blocks).
- The system uses an in-memory **buffer pool** to cache pages fetched from disk.
 - Its job is to manage the movement of those pages back and forth between disk and memory.




Buffer Pool

- When a query accesses a page, the DBMS checks to see if that page is already in memory:
 - ▶ If it's not, then the DBMS must retrieve it from disk and copy it into a <u>frame</u> in its buffer pool.
 - ► If there are no free frames, then find a page to evict.
 - ▶ If the page being evicted is dirty, then the DBMS must write it back to disk.
- Once the page is in memory, the DBMS translates any <u>on-disk addresses</u> to their in-memory addresses.



























Buffer Pool

- Every tuple access goes through the buffer pool manager regardless of whether that data will always be in memory.
 - Always translate a tuple's record id to its memory location.
 - Worker thread must <u>pin</u> pages that it needs to make sure that they are not swapped to disk.



Disk-Oriented DBMS Overhead






In-memory DBMS

- Assume that the primary storage location of the database is permanently in memory.
- Early ideas proposed in the 1980s but it is now feasible because DRAM prices are low and capacities are high.
- First commercial in-memory DBMSs were released in the 1990s.
 - **Examples:** TimesTen, DataBlitz, Altibase



Storage Access Latencies



Reference




In-Memory DBMS: Data Organization




- An in-memory DBMS does not need to store the database in slotted pages but it will still organize tuples in pages:
 - **Direct memory pointers** vs. record ids
 - Fixed-length vs. variable-length data memory pools Use checksums to detect software errors from trashing the database.
- The OS organizes memory in pages too. We already covered this.

In-Memory DBMS: Data Organization



In-Memory DBMS: Data Organization



Persistent Memory DBMSs

Importance of Hardware

- People have been thinking about using hardware to accelerate DBMSs for decades.
 - 1980s: Database Machines
- 2000s: FPGAs + Appliances
- 2010s: FPGAs + GPUs
- **√** 2020s: PM + FPGAs + GPUs + CSAs + More!
- Reference



Persistent Memory



- Emerging storage technology that provide low latency read/writes like DRAM, but with persistent writes and large capacities like SSDs.
 - a.k.a., Non-Volatile Memory, Storage-class Memory
- First-generation devices were block-addressable
- Second-generation devices are byte-addressable






Persistent Memory

- Block-addressable Optane SSD
 - NVM Express works with PCI Express to transfer data to and from Optane SSDs
 - NVMe enables rapid storage in SSDs and is an improvement over older HDD-related interfaces (*e.g.*, Serial Attached SCSI (**SAS**) and Serial ATA (**SATA**))
- Byte-addressable Optane DIMMs
 - New assembly instructions and hardware support



Fundamental Elements of Circuits






Fundamental Elements of Circuits

- In 1971 Leon Chua at Berkeley predicted the existence of a fourth fundamental element.
- A two-terminal device whose resistance depends on the voltage applied to it, but when that voltage is turned off it **permanently remembers** its last resistive state.
- Reference



Fundamental Elements of Circuits





Memristors

- A team at HP Labs led by Stanley Williams stumbled upon a nano-device that had weird properties that they could not understand.
- It wasn't until they found Chua's 1971 paper that they realized what they had invented.
- Reference
- Video



NVM Technologies

- Phase-Change Memory (PRAM)
- Resistive RAM (ReRAM)
- Magnetoresistive RAM (MRAM)



Phase-Change Memory

- Storage cell is comprised of two metal electrodes separated by a resistive heater and the phase change material (chalcogenide).
- The value of the cell is changed based on how the material is heated.
 - A short pulse changes the cell to a ′0′.
 A long, gradual pulse changes the cell to a ′1′.
- Reference





Resistive RAM

- Two metal layers with two TiO2 layers in between.
- Running a current one direction moves electrons from the top TiO2 layer to the bottom, thereby changing the resistance.
- Potential programmable storage fabric...
 - Bertrand Russell's Material Implication Logic
- Reference





Magnetoresistive RAM

- Stores data using magnetic storage elements instead of electric charge or current flows.
- Spin-Transfer Torque (STT-MRAM) is the leading technology for this type of PM.
 - Supposedly able to scale to very smallsizes (10nm) and have **SRAM**-like latencies. What is SRAM used for?
- Reference






Why This is for Real

• Industry has agreed to standard technologies


- and form factors (JDEC). Linux and Microsoft added support for PM in







PM Configurations





PM for Database Systems

- Block-addressable PM is not that interesting.
- Byte-addressable PM will be a game changer but will require some work to use correctly.
 - ▶ In-memory DBMSs will be better positioned to use byte-addressable PM.
 - Disk-oriented DBMSs will initially treat PM as just a faster SSD.



Storage & Recovery Methods

- Understand how a DBMS will behave on a system that only has byte-addressable PM.
- Develop PM-optimized implementations of standard DBMS architectures.
- Based on the N-Store prototype DBMS.
- Reference




Synchronization

- Existing programming models assume that any write to memory is non-volatile.
 - CPU decides when to move data from caches to DRAM.
- The DBMS needs a way to ensure that data is flushed from caches to PM.



Synchronization






Synchronization

- Cache-line Flush (CLFLUSH)
 - ► This instruction allows the DBMS to flush a cache-line out to memory.
 - If that cache line contains modified data at any level of the cache hierarchy, that data is written back to memory.
- Cache-line Write Back (CLWB)
 - Writes back the cache line (if modified) to memory
 - The cache line may be retained in the cache hierarchy in non-modified state
 - ► Improves performance by reducing cache misses
 - CLWB instruction is ordered only by store-fencing (SFENCE) operation.
 - Asynchronous DRAM Refresh (ADR)
 - In case of a power loss, there is sufficient reserve power to flush the stores pending in the memory controller back to Optane DIMM.
 - ▶ Stores are posted to the Write Pending Queue (WPQ) in the memory controller
- Reference



Naming


• If the DBMS process restarts, we need to make sure that all the pointers for in-memory data point to the same data.





Naming

• If the DBMS process restarts, we need to make sure that all the pointers for in-memory data point to the same data.



ASR



PM-Aware Memory Allocator

Feature 1: Synchronization

- ► The allocator writes back CPU cache lines to PM using the CLFLUSH instruction.
- ▶ It then issues a SFENCE instruction to wait for the data to become durable on PM.

Feature 2: Naming

► The allocator ensures that virtual memory addresses assigned to a memory-mapped region never change even after the OS or DBMS restarts.



Storage Engine Architectures

Storage Engine Architectures

Choice 1: In-place Updates

- ► Table heap with a write-ahead log + snapshots.
- Example: VoltDB

Choice 2: Copy-on-Write

- Create a shadow copy of the table when updated.
- No write-ahead log.
- Example: LMDB

Choice 3: Log-structured

- All writes are appended to log. No table heap.
- Example: RocksDB








































PM-Aware Architectures

- Leverage the allocator's <u>non-volatile pointers</u> to only record <u>what</u> changed rather than <u>how</u> it changed.
- The DBMS only must maintain a transient UNDO log for a txn until it commits.
 - Dirty cache lines from an uncommitted txn can be flushed by hardware to the memory controller.
 - ▶ **No REDO log** because we flush all the changes to PM at the time of commit.




PM-Aware In-place Updates Engine






PM-Aware In-place Updates Engine







PM-Aware In-place Updates Engine






















- Limitations
 - Expensive Copies




PM-Aware Copy-On-Write Engine








PM-Aware Copy-On-Write Engine







705














• Limitations

Duplicate Data

Compactions




PM-Aware Log-Structured Engine





PM-Aware Log-Structured Engine





PM Summary

- Optimization of Storage Engine Architectures
 - Leverage byte-addressability to avoid unnecessary data duplication.

pensstre





Conclusion

Stry me why

- The design of a in-memory DBMS is significantly different than a disk-oriented system.
- The world has finally become comfortable with in-memory data storage and processing.
- Byte-addressable PM is going to be a game changer.
- We are likely to see many new computational components that DBMSs can use in the next decade.
 - ► The core ideas / algorithms will still be the same.

