


Lecture 11: Persistent Memory Databases

CREATING THE NEXT®

Today's Agenda

Persistent Memory Databases

- 1.1 Recap
- 1.2 Disk-oriented vs In-Memory DBMSs
- 1.3 Persistent Memory DBMSs1.4 Storage Engine Architectures
- 1.5 Write-Behind Logging
- 1.6 Conclusion



Recap

Larger-than-Memory Databases

- Allow an in-memory DBMS to store/access data on disk without bringing back all the slow parts of a disk-oriented DBMS.
 - Minimize the changes that we make to the DBMS that are required to deal with disk-resident data
 - It is better to have only the **buffer manager** deal with moving data around
 - Rest of the DBMS can assume that data is in DRAM.
- Need to be aware of hardware access methods
 - ► In-memory Access = **Tuple**-Oriented.
 - Disk Access = Block-Oriented.





Today's Agenda

- Disk-oriented vs In-Memory DBMSs
- Persistent Memory DBMSs
- Storage Engine Architectures
- Write-Behind Logging



Disk-oriented vs In-Memory DBMSs

Background

- Much of the development history of DBMSs is about dealing with the limitations of hardware.
- Hardware was much different when the original DBMSs were designed in 1970s:
 - Uniprocessor (single-core CPU)
 - DRAM capacity was very limited.
 - ► The database had to be stored on disk.
 - Disks were even slower than they are now.



Background

- But now DRAM capacities are large enough that most databases can fit in memory.
 - Structured data sets are smaller.
- We need to understand why we can't always use a "traditional" disk-oriented DBMS with a large cache to get the best performance.



Disk-Oriented DBMS

- The primary storage location of the database is on non-volatile storage (*e.g.*, HDD, SSD).
- The database is organized as a set of fixed-length pages (aka blocks).
- The system uses an in-memory **buffer pool** to cache pages fetched from disk.
 - Its job is to manage the movement of those pages back and forth between disk and memory.







Buffer Pool

- When a query accesses a page, the DBMS checks to see if that page is already in memory:
 - If it's not, then the DBMS must retrieve it from disk and copy it into a frame in its buffer pool.
 - ► If there are no free frames, then find a page to evict.
 - If the page being evicted is dirty, then the DBMS must write it back to disk.
- Once the page is in memory, the DBMS translates any on-disk addresses to their in-memory addresses.



























Buffer Pool

- Every tuple access goes through the buffer pool manager regardless of whether that data will always be in memory.
 - ► Always translate a tuple's record id to its memory location.
 - Worker thread must <u>pin</u> pages that it needs to make sure that they are not swapped to disk.



Disk-Oriented DBMS Overhead



Reference



In-memory DBMS

- Assume that the primary storage location of the database is permanently in memory.
- Early ideas proposed in the 1980s but it is now feasible because DRAM prices are low and capacities are high.
- First commercial in-memory DBMSs were released in the 1990s.
 - Examples: TimesTen, DataBlitz, Altibase



Storage Access Latencies

	L3	DRAM	SSD	HDD
,	20 ns		,	10,000,000 ns
Write Latency	20 ns	ou ns	300,000 ns	10,000,000 ns

Reference




In-Memory DBMS: Data Organization

- An in-memory DBMS does <u>not</u> need to store the database in slotted pages but it will still organize tuples in pages:
 - **Direct memory pointers** vs. record ids
 - Fixed-length vs. variable-length data memory pools
 - ► Use checksums to detect software errors from trashing the database.
- The OS organizes memory in pages too. We already covered this.






In-Memory DBMS: Data Organization





In-Memory DBMS: Data Organization





Persistent Memory DBMSs

Importance of Hardware

- People have been thinking about using hardware to accelerate DBMSs for decades.
- 1980s: Database Machines
- 2000s: FPGAs + Appliances
- 2010s: FPGAs + GPUs
- 2020s: PM + FPGAs + GPUs + CSAs + More! Reference



Persistent Memory

- Emerging storage technology that provide low latency read/writes like DRAM, but with persistent writes and large capacities like SSDs.
 - ▶ a.k.a., Non-Volatile Memory, Storage-class Memory
- First-generation devices were block-addressable
- Second-generation devices are byte-addressable




Persistent Memory

- Block-addressable Optane SSD
 - NVM Express works with PCI Express to transfer data to and from Optane SSDs
 - NVMe enables rapid storage in SSDs and is an improvement over older HDD-related interfaces (e.g., Serial Attached SCSI (SAS) and Serial ATA (SATA))
- Byte-addressable Optane DIMMs
 - New assembly instructions and hardware support



Fundamental Elements of Circuits






Fundamental Elements of Circuits

- In 1971, Leon Chua at Berkeley predicted the existence of a fourth fundamental element.
- A two-terminal device whose resistance depends on the voltage applied to it, but when that voltage is turned off it **permanently remembers** its last resistive state.
- Reference



Fundamental Elements of Circuits





Memristors

- A team at HP Labs led by Stanley Williams stumbled upon a nano-device that had weird properties that they could not understand.
- It wasn't until they found Chua's 1971 paper that they realized what they had invented.
- Reference
- Video



NVM Technologies

- Phase-Change Memory (PRAM)
- Resistive RAM (ReRAM)
- Magnetoresistive RAM (MRAM)



Phase-Change Memory

- Storage cell is comprised of two metal electrodes separated by a resistive heater and the phase change material (chalcogenide).
- The value of the cell is changed based on how the material is heated.
 - A short pulse changes the cell to a '0'.
 - ► A long, gradual pulse changes the cell to a '1'.
- Reference





Resistive RAM

- Two metal layers with two TiO2 layers in between.
- Running a current one direction moves electrons from the top TiO2 layer to the bottom, thereby changing the resistance.
- Potential programmable storage fabric...
 - Bertrand Russell's Material Implication Logic
- Reference





Magnetoresistive RAM

- Stores data using magnetic storage elements instead of electric charge or current flows.
- Spin-Transfer Torque (STT-MRAM) is the leading technology for this type of PM.
 - Supposedly able to scale to very smallsizes (10nm) and have **SRAM**-like latencies. What is SRAM used for?


Reference






Why This is for Real

- Industry has agreed to standard technologies and form factors (JDEC).
- Linux and Microsoft added support for PM in their kernels (DAX).
- Intel added new instructions for flushing cache lines to PM (CLFLUSH, CLWB).





PM Configurations





PM for Database Systems

- Block-addressable PM is not that interesting.
- Byte-addressable PM will be a game changer but will require some work to use correctly.
 - ▶ In-memory DBMSs will be better positioned to use byte-addressable PM.
 - Disk-oriented DBMSs will initially treat PM as just a faster SSD.



Storage & Recovery Methods

- Understand how a DBMS will behave on a system that only has byte-addressable PM.
- Develop PM-optimized implementations of standard DBMS architectures.
- Based on the N-Store prototype DBMS.
- Reference




Synchronization

- Existing programming models assume that any write to memory is non-volatile.
 - CPU decides when to move data from caches to DRAM.
- The DBMS needs a way to ensure that data is flushed from caches to PM.



Synchronization





Synchronization


Cache-line Flush (CLFLUSH)

- ► This instruction allows the DBMS to flush a cache-line out to memory.
- If that cache line contains modified data at any level of the cache hierarchy, that data is written back to memory.
- Cache-line Write Back (CLWB)
 - Writes back the cache line (if modified) to memory
 - ► The cache line may be retained in the cache hierarchy in non-modified state
 - Improves performance by reducing cache misses
 - LUWB instruction is ordered only by store-fencing (SFENCE) operation.
- Asynchronous DRAM Refresh (ADR)
 - In case of a power loss, there is sufficient reserve power to flush the stores pending in the memory controller back to Optane DIMM.
 - Stores are posted to the Write Pending Queue (WPQ) in the memory controller

Reference


Naming

 If the DBMS process restarts, we need to make sure that all the pointers for in-memory data point to the same data.



Naming

• If the DBMS process restarts, we need to make sure that all the pointers for in-memory data point to the same data.





PM-Aware Memory Allocator




- Feature 1: Synchronization
 - ► The allocator writes back CPU cache lines to PM using the CLFLUSH instruction.
 - ▶ It then issues a SFENCE instruction to wait for the data to become durable on PM.
- Feature 2: Naming
 - ► The allocator ensures that virtual memory addresses assigned to a memory-mapped region never change even after the OS or DBMS restarts.



Storage Engine Architectures

Storage Engine Architectures



- ► Table heap with a write-ahead log + snapshots.
- Example: VoltDB


Choice 2: Copy-on-Write Create a shadow copy of the table when updated

- No verite aboad log
- No write-ahead log.
- Example: LMDB


 Choice 3: Log-structured
 - All writes are appended to log. No table heap.
 - Example: RocksDB























- Limitations
 - Duplicate Data
 - Recovery Latency




PM-Aware Architectures

- Leverage the allocator's non-volatile pointers to only record what changed rather than **how** it changed.
- The DBMS only must maintain a transient **UNDO log** for a txn until it commits.
 - Dirty cache lines from an uncommitted txn can be flushed by hardware to the memory controller.
 - ▶ No REDO log because we flush all the changes to PM at the time of commit.




PM-Aware In-place Updates Engine






PM-Aware In-place Updates Engine







PM-Aware In-place Updates Engine
























- Limitations
 - Expensive Copies




PM-Aware Copy-On-Write Engine







PM-Aware Copy-On-Write Engine



















- Limitations
 - Duplicate Data
 - Compactions




PM-Aware Log-Structured Engine





PM-Aware Log-Structured Engine







Write-Behind Logging

Observation

- WAL serves two purposes
- Transform random writes into sequential log writes.
 - Support transaction rollback.
 - Design makes sense for disks with slow random writes.
- But PM supports fast random writes
 - Directly write data to the multi-versioned database.
 - Only record <u>meta-data</u> about committed txns in log.

MUCL


CTR

Write-Behind Logging

- PM-centric logging protocol that provides instant recovery and minimal duplication overhead.
 - Directly propagate changes to the database.
 - Only record meta-data in log.
 - Reference
- Recover the database almost instantaneously.
 - Need to record meta-data about in-flight transactions.
 - ► In case of failure, ignore their effects.




Write-Behind Logging






Write-Behind Logging





Write-Behind Logging



- DBMS assigns timestamps to transactions
 - Get timestamps within same group commit timestamp range to identify and ignore effects of in-flight txns.
- Use failed group commit timestamp range:
 - DBMS uses range during tuple visibility checks.
 - Ignores tuples created or updated within this range.
 - UNDO is implicitly done via visibility checks.



Write-Behind Logging




- Recovery consists of only analysis phase
 - The DBMS can immediately start processing transactions after restart with explicit UNDO/REDO phases.
- Garbage collection eventually kicks in to remove the physical versions of uncommitted transactions.
 - Using timestamp range information in write-behind log.
 - After this finishes, no need to do extra visibility checks.




- Use group commit timestamp range to ignore effects of transactions in failed group commit.
 - Maintain list of failed timestamp ranges.




7, 17















Write-Behind Logging – Recovery

- Replay Log with 1m TPC-C Transactions
- PM 2× Latency Relative to DRAM



Write-Behind Logging – Runtime

- TPC-C Transactions (Eight Warehouses)
- PM 2× Latency Relative to DRAM





Conclusion

PM Summary

- Optimization of Storage Engine Architectures
 - Leverage byte-addressability to avoid unnecessary data duplication.
- Optimization of Logging and Recovery Protocol
 - PM-optimized recovery protocols avoid the overhead of processing a log.
 - Non-volatile data structures ensure consistency.





Parting Thoughts

- The design of a in-memory DBMS is significantly different than a disk-oriented system.
- The world has finally become comfortable with in-memory data storage and processing.
- Byte-addressable PM is going to be a game changer.
- We are likely to see many new computational components that DBMSs can use in the next decade.
 - ► The core ideas / algorithms will still be the same.





Next Class

Concurrency Control

